

?SFTP / FTP (Remote File Access)

Here at Atomic Host we offer a built in file manager. However we do also offer SFTP (Secure File Transfer Protocol). This allows you to use software on your computer, In our case we recommend using [WinSCP](#) as it is free to download.

WinSCP Connect (EASY)


Software

Firstly, install your FTP / SFTP software of choice, we highly recommend using [WinSCP](#) as it is free to download. You may use a different preferred software instead.

Connect to SFTP


Head over to your servers [Settings](#) Page and click on the [Change Password](#) Button

After changing your password click on the [Launch SFTP](#) button >> This should launch WinSCP



The screenshot shows a dark-themed interface for SFTP details. At the top left, it says "SFTP Details". Below this, there are two input fields: "Username" and "Address". Both fields contain text that has been redacted with blue scribbles. At the bottom of the form, there are two buttons: a red button labeled "Launch SFTP" and a yellow button labeled "Change Password".

When WinSCP loads up, you can now t



change password button, then hit

You should now have full access to your servers files!

Manually connect to SFTP (HARD)

Where can i find my SFTP Details?

You can find your SFTP Details by navigating to:

Your Server >> Settings >> SFTP

Here you will see your **Host name**, **Port** and **Username**. If this is your first time using SFTP on this server, please click the Button.

How to connect to SFTP with FileZilla

When you have opened FileZilla, Navigate to

File >> Site Manager

On the left you will see all your sites / servers you can connect too. We need to add your server to this list, so to do so press

New Site

Next, make sure the following settings are as shown

Protocol: SFTP - SSH File Transfer Protocol

Host: HOST-NAME-HERE PORT: 2022

Logon Type: Normal

User: USER-NAME-HERE

Password: PASSWORD-HERE

You can optionally add a comment. Otherwise, you can press

OK

Now. To connect to your SFTP, you can navigate back to

File >> Site Manager

then single left click on your new server entry, then press

Connect

If you have any problems, don't hesitate to contact our staff!

Revision #1

Created 2025-10-30 14:11:34 UTC by Fin

Updated 2025-10-30 14:18:20 UTC by Fin